# Outlook 2007 Configuration for your gmail account

## Minimum requirement

- Gmail account and password
- Outlook setup install on your Computer
- 1) Search outlook in you pc and open it

vebmail-c	/
Programe (1)	
Mail 2 Select outlook Go online to get Windows Live Essentials	1.0
Microsoft Office OneNote (24) Outlook configuration to Gmail Outlook configuration to Webmail O 06-1-2016	
Microsoft Office Outlook (136) Microsoft Office Outlook Test Message 2.40 Microsoft Office Outlook Test Message	
Files (1)	
See more results	
Shut down >	

### 2) Now Click Next



3) Select "yes" and click next



4)	<b>Below mention</b>	from shall	display	now enter	your information	า
					5	

Auto Account Setu; Clicking Next will c Exchange server a	) ontact your e-mail server and configure your Internet service provid account settings.	der or Microsoft
Your Name:	Example: Barbara Sankovic	lame
-mail Address:	Email i Example: barbara@contoso.com	d
Password:	passw	ord
Retype Password:	Type the password your Internet service provider has given you	ord

Click Next. If you are configuring Outlook 2007 automatically, you're done! Just click Finish.

If you are configuring Outlook 2007 manually, select Internet E-mail and click Next.

1. Verify your User Information, and enter the following additional information:

#### Server Information

#### Account Type: POP3

**Incoming mail server:** pop.gmail.com (Google Apps users, enter the server names provided, don't add your domain name in these steps)

Outgoing mail server (SMTP): smtp.gmail.com

#### **Logon Information**

**User Name:** Enter your Gmail username (including @gmail.com). Google Apps users, enter your full address in the format *username@your\_domain.com* 

**Password:** Enter your email password.

#### Require logon using Secure Password Authentication (SPA): Leave this option

unchecked.

## 5) Enter all your Details

User Information		Test Account Settings
Your Name:	User Name	After filling out the information on this screen, we
E-mail Address:	username@gmail.com	button below. (Requires network connection)
Server Information		
Account Type:	POP3	Lest Account Settings
ncoming mail server:	pop.gmail.com	
Outgoing mail server (SMTP	): smtp.gmail.com	
Logon Information		
Jser Name:	username@gmail.com	
eassword:	***********	

- 1. Click the More Settings... button, and select the Outgoing Server tab.
- 2. Check the box next to **My outgoing server (SMTP) requires authentication** and select **Use same settings as my incoming mail server.**

eneral	Outgoing Se	rver	Connection	Advanced		
My ou	tgoing serve	r (SMT	P) requires a	uthenticatio	n	
⊙ <u>∪</u> s	e same setti	ngs as	my incoming	mail server		
OLo	g on using	2727-27	000000	000000	00000	
Us	ser <u>N</u> ame:					
Pa	assword:					
		Rem	ember passv	word		
OLO	]Reguire Se	cure Pa ning ma	assword Auti	nentication ( fore sending	SPA) mail	
OLO	Reguire Se	cure Pa	il server bet	nentication (	SPA) mail	

- 1. Click the **Advanced tab**, and check the box next to **This server requires an encrypted connection (SSL)** under **Incoming Server (POP3)**.
- 2. In the **Outgoing server (SMTP)** box, enter 587, and select **TLS** from the drop-down menu next to **Use the following type of encrypted connection:**.

General (	Outgoing Server Connection Advanced
Server Por	t Numbers
Incoming	server (POP3): 995 Use Defaults
✓ 11	his server requires an <u>encrypted</u> connection (SSL)
<u>O</u> utgoing	server (SMTP): 587
Use t	the following type of engrypted connection: TLS
Server <u>T</u> im	eouts
Short	Long 1 minute
Delivery –	
Leave	a copy of messages on the server
R	emove from server after 10 🔿 days
R	emove from server when deleted from 'Deleted Items'

- 1. Click **OK**.
- 2. Click **Test Account Settings...** After receiving 'Congratulations! All tests completed Successfully', click Close.
  Click Next, and then click Finish.

Congratulations! You're done configuring your client to send and retrieve Gmail messages.